

- E.) Start adding the desired burst comp.
- a.) Pour in about 1/3 of the comp. and work it into the damp cotton seeds. It will get gooey at first, but drier as more comp. is added. Work in the comp. until all the seeds are evenly coated and shiny black in color. If there are any white spots, it means that the seeds were not soaked enough and that there are dry spots on them. Not much can be done to remedy this.
  - b.) Sprinkle in another 1/3 of the comp. and work it into the seeds. Use a tossing motion from the bottom of the bowl to get the comp. evenly into the seeds. You will notice that the seeds aren't so gooey anymore and don't stick together.
  - c.) Add about half of the remaining 1/3 of comp. and work it into the seeds. If by chance you squeezed out too much water, and the seeds are failing to pick up the dry comp., you can add water a little at a time with a spray bottle until the comp. is picked up.
  - d.) Add the remaining comp. and keep tossing the seeds, turning them over from the bottom of the bowl, until all the comp. is picked up. Keep working them to insure that all the comp. dust is on the seeds.
- F.) Transfer the coated seeds onto a few layers of newspaper and spread them out to dry. Dry them in the shade. They should dry in one afternoon if the humidity is not too high. It also helps to turn them over a few times during the drying process.

**PLEASE NOTE THAT THE DRIED BURST CHARGE IS EXTREMELY EXPLOSIVE AND CAUTION IS ADVISED IN HANDLING IT!!**

**--WARNING!--**

**THIS INFORMATION IS GIVEN FOR REFERENCE ONLY TO INTERESTED PARTIES FOR THEIR OWN KNOWLEDGE. MAKING FIREWORKS IS DANGEROUS AND PERSONS USING THIS INFORMATION SHOULD FOLLOW ALL FEDERAL AND STATE LAWS PERTAINING TO MANUFACTURING FIREWORKS!**

**THE AUTHOR SHALL NOT BE HELD RESPONSIBLE FOR ANY ACCIDENT, DAMAGE OR INJURY CAUSED BY THE USE OF THIS INFORMATION!**